

Upgrading Guiffy on a computer running RazorPC

These instructions may be used to upgrade the Guiffy diff/merge utility on a Windows 7/8/10 computer. It is assumed that RazorPC version 5.4.01 has already been installed on the computer.

Download the Guiffy executable from the following web site:


http://visiblesystemscorp.com/Download/Razor/guiffy_download.htm

NOTE: Select the download file for Windows with JRE included (normally at the top of the downloads list)

NOTE: Choose the 32-bit version of Guiffy.

Make sure the Razor clients on this PC are not running and then open Windows Explorer and navigate to the following directory:

C:\Program Files (x86)\Visible Systems\ThirdParty\Guiffy




NOTE: The directory is C:\Program Files (x86)\Visible\ThirdParty\Guiffy on a Windows 7/8/10 computer


Select and remove ALL of the sub-folders and files from the Guiffy folder (e.g. the Guiffy folder should exist but be empty after this step). The Java software is under the ire folder and will be removed along with the the Guiffy files.

Close Windows Explorer


Select and run the Guiffy executable (e.g. guf105.exe or a newer version)




click Next




Accept the license agreement and click Next




Change the install directory to C:\Program Files (x86)\Visible Systems\ThirdParty\Guiffy and click Next




Select "Don't create icons" and click Next



Click Install





Click Done