

Upgrading Guiffy on a computer running RazorPC

These instructions may be used to upgrade the Guiffy diff/merge utility on a Windows XP or Windows 7/8/10 computer. It is assumed that RazorPC version 5.3.03 has already been installed on the computer.


Download the Guiffy executable from the following web site:

http://www.visible.com/Download/Razor/guiffy_download.htm

NOTE: Select the download file for Windows with JRE included (normally at the top of the web page)

NOTE: Choose the 32-bit version of Guiffy (e.g. Windows - XP, 2003, Vista, 2008, 7, 2012, 8, 10 (x86 32 bit))


Open the Microsoft Add or Remove Programs utility and remove Guiffy



NOTE: The name may be listed as Guiffy 7.0(3rd party File comparison software)

Open Windows Explorer and navigate to the following directory:

C:\Program Files\Visible\ThirdParty\Guiffy




NOTE: The directory is C:\Program Files (x86)\Visible\ThirdParty\Guiffy on a Windows 7/8/10 computer


Select and remove ALL of the sub-folders and files from the Guiffy folder (e.g. the Guiffy folder should exist but be empty after this step). The Java software is under the ire folder and will be removed along with the the Guiffy files.

Close Windows Explorer


Select and run the Guiffy executable (e.g. guf105.exe)



click Next




Accept the license agreement and click Next



Change the install directory to C:\Program Files\Visible\ThirdParty\Guiffy and click Next


NOTE: The directory is C:\Program Files (x86)\Visible\ThirdParty\Guiffy on a Windows 7/8/10 computer.



Select "Don't create icons" and click Next



Click Install





Click Done